

## NAME

osl/sdosl – CUTER interface with the OSL solver.

## SYNOPSIS

```
[sd]osl [-decode] [-s] [-n] [-h] [-k] [-r] [-o 0|1] [-l secs] [-f] [-b] [-a 1|2] [-show] [[-param  
name=value[,name=value...]] [-force]] [-debug] [-Lpath/to/lib] [--blas keyword] [--lapack keyword]  
[problem[.SIF]]
```

## DESCRIPTION

*sdosl* interfaces the OSL solver with the CUTER tools and SIF-encoded problems. *sdosl* applies the SIF decoder to the problem *problem.SIF* to produce the OUTSDIF.d file and the problem-dependant Fortran subroutines. If *problem.SIF* has already been decoded, the script *osl* may be run by itself. OSL solves large-scale linear, convex quadratic, and mixed-integer programs.

*sdosl* is only included for backward compatibility with earlier versions of CUTE, and simply calls *osl* with the *-decode* flag.

*osl* links all the needed libraries and modules for the OSL solver to solve the problem decoded from the SIF file and generates the executable.

## [sd]osl Options

You can start [sd]osl with the following options:

### **-decode**

Applies the SIF decoder to the problem *problem.SIF* to produce the OUTSDIF.d file and the problem-dependant Fortran subroutines. It is redundant to call *sdosl* with the *-decode* flag.

**-s** Run [sd]osl in single-precision mode if available. Double precision is the default.

**-n** Use the load module if it already exists. Compiling a new load module is the default.

**-h** Print a short help message.

**-k** Keep the generated executable after use. May be useful when solving a particular problem with the same solver with different parameters. Deleting the executable after use is the default.

**-r** Discourage recompilation of the test problem. Default is to recompile object files.

**-o *0|1***

Regulates the output level of [sd]osl. Verbose mode is **-o 1**, silent mode is **-o 0**. Silent mode is the default.

**-l *secs***

sets a limit of *secs* second on OSL runtime. Unlimited cputime is the default.

**-f** Use automatic differentiation in Forward mode

**-b** Use automatic differentiation in Backward mode

**-a *1|2***

**-a 1** uses the older HSL automatic differentiation package AD01 and **-a 2** uses the newer HSL automatic differentiation package AD02. **-a 2** is the default.

**-show**

displays possible parameter settings for *problem[.SIF]*. Other options are ignored.

**-param**

cast *problem[.SIF]* against explicit parameter settings. Several parameter settings may be given as a comma-separated list following **-param** or using several **-param** flags. Use *sifdec -show problem* to view possible settings. If a setting is not allowed in the SIF file, no action is taken unless *-force* is present.

**-force**

Forces the setting of the parameters named using *-param* to the given values, even if those values are not predefined in the SIF file.

**-Lpath/to/lib**

This option is passed directly to the linker and causes the path *path/to/lib* to be searched for libraries.

**--blas keyword**

Overrides usage of the default *linpack* library packaged with CUTER. Instead, use the BLAS library specified by *keyword*. The keyword *keyword* has one of two forms. The first, *-lmyblas* causes the linker to search for BLAS subprograms in the *libmyblas.a* library. The second, *none*, causes the linker to skip inclusion of any external BLAS. Use the first option if an optimized BLAS library is available on the host system, e.g., the ATLAS BLAS. The second option is useful for packages which already include the necessary BLAS subprograms.

**--lapack keyword**

Overrides usage of the default *linpack* library packaged with CUTER. Instead, use the LAPACK library specified by *keyword*. The keyword *keyword* has one of two forms. The first, *-lmylapack* causes the linker to search for LAPACK subroutines in the *libmylapack.a* library. The second, *none*, causes the linker to skip inclusion of any external LAPACK. Use the first option if an optimized LAPACK library is available on the host system. The second option is useful for packages which already include the necessary LAPACK subprograms.

*problem*

*problem.SIF* is the name of the file containing the SIF information on the problem to be solved.

**ENVIRONMENT****CUTER**

Home directory for CUTER

**MYCUTER**

Home directory of the installed CUTER distribution.

**MASTSIF**

A pointer to the directory containing the CUTER problems collection. If this variable is not set, the current directory is searched for *problem.SIF*. If it is set, the current directory is searched first, and if *problem.SIF* is not found there, \$MASTSIF is searched.

**AUTHORS**

A.R. Conn, N.I.M. Gould, D. Orban and Ph.L. Toint

**NOTES**

OSL is distributed by International Business Machines, subject to certain license agreements. OSL is copyrighted by IBM Corporation.

**SEE ALSO**

*CUTER (and SifDec): A Constrained and Unconstrained Testing Environment, revisited*,  
N.I.M. Gould, D. Orban and Ph.L. Toint,  
ACM TOMS, **29**:4, pp.373-394, 2003.

*CUTE: Constrained and Unconstrained Testing Environment*,  
I. Bongartz, A.R. Conn, N.I.M. Gould and Ph.L. Toint,  
TOMS, **21**:1, pp.123-160, 1995.

*Optimization Subroutine Library: Guide and Reference, SC23-0519-1*,  
International Business Machines Corporation,  
IBM Corporation, second edition, 1990.

sifdecode(1), gen(1).